



## User Manual Arcmap Add-In

Datum: 10 januari 2014  
CycloMedia Technology B.V. | T +31 (418) 556100 | E: [info@cyclomedia.com](mailto:info@cyclomedia.com)

# Index

Index .....	2
1. Installation .....	3
2. How to use the Add-In .....	6
2.1 Show Cyclorama images .....	6
2.1.1 Show recent Cyclorama layer .....	6
2.1.2 Show historical Cyclorama layer .....	6
2.1.3 Open a Cyclorama image .....	7
2.2 Show Vector data .....	9
2.3 Measurement .....	10
2.3.1 Standaard measurement – Point measurement .....	10
2.3.2 Standaard measurement – Line / Surface measurement .....	12
2.3.3 Smart click measurement – Point measurement .....	14
2.3.4 Smart click measurement – Line / Surface measurement .....	16
2.3.5 Import a measurement back in a Cyclorama .....	18

# 1. Installation

You have to do these steps to install the Add-In successfully:

- 1) Check if 'Adobe Flash Player' is installed on your machine. If flash player is not, installed, install 'Adobe Flash Player'.
- 2) If you have installed a previous version of the Add-In, first delete the previous version of the Add-In:
  - I. Start ArcMap.
  - II. Customize -> Add-In Manager (Figure 1)




Figure 1: Add-In Manager

- III. Select the Cyclorama Add-In and click on the button: <Delete this Add-In>
  - IV. Exit ArcMap
- 3) Double-click the add-In and select <Install Add-In> to install the Add-In. (Figure 2)





Figure 2: Add-In installation

- 4) Start ArcMap.
- 5) Select the menu: Customize -> Extensions. (Figure 3).



**Figure 3: Extensions menu**

- 6) Checkmark: 'CycloMedia Cyclorama – ArcMap Integration' and close the menu.
- 7) Then select the Cyclorama toolbar: Customize -> toolbars -> Cyclorama. (Figure 4)




**Figure 4: Cyclorama toolbar**

- 8) Select the 'CycloMedia Options' icon (Figure 5) of the Cyclorama toolbar. You get the 'CycloMedia Options' form. (Figure 6)




**Figure 5: The selected 'CycloMedia options' icon**



**Figure 6: The CycloMedia Options form**

- 9) Enter your username and password and press: <Apply>
- 10) If you see 'Login Successfully', you are logged in.
- 11) Select the 'Cyclorama viewer' tab of the CycloMedia Options form. (Figure 7)



**Figure 7: The Cyclorama viewer tab**

- 12) Select the special reference which the viewer must use.
- 13) Press <Apply> and the changes take effect.
- 14) Now you are ready for use the Add-In.


## 2. How to use the Add-In

### 2.1 Show Cyclorama images

#### 2.1.1 Show recent Cyclorama layer


You have to do these steps to show the recent Cyclorama layer in the map:

- 1) Select in the Cyclorama toolbar: 'Add recent cyclorama layer'(Figure 8).



**Figure 8: The selected 'Add Recent Cyclorama Layer' icon**

- 2) In the 'Table of contents – layers' screen appears a 'CycloMedia - Recent Recordings' layer (Figure 9).



**Figure 9: The CycloMedia - Recent Recordings Layer**

- 3) Zoom in on the map and if you have reached a zoom level of 1:2000, you will see dots on the map. (With the condition that there are recordings in that area)

#### 2.1.2 Show historical Cyclorama layer


You have to do these steps to show the historical Cyclorama layer in the map:

- 1) Select in the Cyclorama toolbar: 'Add historical cyclorama layer'(Figure 10).



**Figure 10: The selected 'Historical' Cyclorama Layer' icon**

- 2) In the 'Table of contents – layers' screen appears a 'CycloMedia - Recent Recordings' layer (Figure 11).




**Figure 11: The CycloMedia - Historical Recordings Layer**

- 3) Zoom in on the map and if you have reached a zoom level of 1:2000, you will see dots on the map. (With the condition that there are recordings in that area)
- 4) The date range of the recordings can be changed with the 'CycloMedia Recording History' form. Select the 'CycloMedia Recording History' form in the Cyclorama toolbar. (Figure 12)



**Figure 12: The selected CycloMedia recording History form**

- 5) You can change the date range in this form. (Figure 13)




**Figure 13: CycloMedia Recording History**

### 2.1.3 Open a Cyclorama image


You have to do these steps to open a Cyclorama image:

- 1) Select the 'Open location tool' in the Cyclorama toolbar (Figure 14).




**Figure 14: The selected 'Open location tool'**

- 2) Click on a dot and the corresponding cyclorama opens (Figure 15).



**Figure 15: Arcmap with 2 open cycloramas**

- 3) Click on another dot and a second corresponding cyclorama opens (Figure 15).  
 4) Click on CycloMedia Options – Cyclorama viewer and the 'Max viewers' option is the option for the max number of viewers which can be opened. (Figure 16)



**Figure 16: Max viewers option /  
Detail images option**

- 5) Some areas are driven with additional cameras. These detailed images can be made visible with the detail images checkmark. (Figure 16)  
 6) Right click on the Recent or Historical Recording layer and the feature layer context menu appears. (Figure 18).  
 7) With The 'Show in Cyclorama' button, the recording points in the Cyclorama can be turned on or off.



## 2.2 Show Vector data

- 1) Add vector data to the map (Points, lines or polygons), vector data can be like:
  - Shape files
  - ArcSDE
  - Personal MDB
  - File GDB
- 2) Open a cyclorama (Figure 17)




Figure 17: Show vector data

- 3) Right click on the vector layer and the feature layer context menu appears (Figure 18)
- 4) With The 'Show in Cyclorama' button, the vector layer in the cyclorama can be turned on and off.
- 5) The distance around the images which the vector layer data is included in the cyclorama can be set in the CycloMedia Options – Cyclorama viewer menu (Dist vect layer – viewer) (Figure 16). The default distance is 30 meters.




Figure 18: feature layer context menu


## 2.3 Measurement

Measurements are stored in vector data layers. Point, line or surface measurements are stored in point, line or polygon vector data layers. The following sections explain in detail the various types of measurements:

- 2.3.1 *Standaard measurement – Point measurement*
- 2.3.2 *Standaard measurement – Line / Surface measurement*
- 2.3.3 *Smart click measurement – Point measurement*
- 2.3.4 *Smart click measurement – Line / Surface measurement*


### 2.3.1 *Standaard measurement – Point measurement*

- 1) Add a point vector data layer to the map where you want to add the measurement.
  - 2) Open two or more images which the object is visible what should be measured.
  - 3) Disable smart click measurement in the CycloMedia Options – Measurement menu.
- (Figure 19)



**Figure 19: Disable smart click measurement**

- 4) Right click on the point vector layer and select: 'Edit Features -> Start Editing'
- (Figure 20)



**Figure 20: Edit features**

- 5) Select the point layer in the Create Features form to start a point measurement.  
(Figure 21)




Figure 21: Create Features

- 6) Select the point you want to measure in the first image.
- 7) Select the point you want to measure in the second image. (Figure 22)




Figure 22: Point measurement (no smart click)

- 8) The selected measurement details form contains information about the measurement.  
(Figure 23)




Figure 23: Selected measurement details form


- 9) The Cyclorama toolbar contains a icon for make the selected measurement details form visible / invisible.

**Figure 24: The selected measurement details icon**




- 10) It is possible now for remove observation points or to add more observation points.
- 11) If you want to add more observation points, open a new image and select in that image the point you want to measure.
- 12) If you are finished, Click the <Close> button down the 'Selected Measurement Details' form. (Figure 25)

**Figure 25: The selected measurement details buttons**



- 13) The measurement point is now added, if you want, you can now measure a second point at the same way.
- 14) If you are finished with measurement, you can save the edits to the vector layer. (Figuur 26)



**Figuur 26: Menu for save and stop editing**

### 2.3.2 Standaard measurement – Line / Surface measurement

- 1) Add a line or a polygon vector data layer to the map where you want to add the measurement.
- 2) Open two or more images which the object is visible what should be measured.


- 3) Disable smart click measurement in the CycloMedia Options – Measurement menu. (Figure 19)
- 4) Right click on the line or polygon vector layer and select: 'Edit Features -> Start Editing' (Figure 20)
- 5) Select the line or polygon layer in the Create Features form to start a line or a surface measurement. (Figure 21)
- 6) Select the first point you want to measure in the first image.
- 7) Then you select the second and the third point you want to measure, until you have done all the points you want to measure in the first image. (Figure 27)



**Figure 27: select step by step all the points in the first image**

- 8) Then you select step by step all the points of the measurement in the second image. (Figure 30)
- 9) The measurement is now complete. If you want to edit some measurement points, click the <Edit> button down the 'Selected Measurement Details' form. (Figure 28)

**Figure 28: The edit button for edit the measurement**



- 10) You can now move through the measurement points with the '<' and the '>' buttons.
- 11) You can add or remove observation points for a selected measurement. (Figure 23)
- 12) If you want to go back to the measurement for add more measurement points or to finished measurement. Click the <Close> button down the 'Selected Measurement Details' form. (Figure 25)
- 13) Click on the "finish sketch" button of the "Feature Construction" menu to close the measurement. (Figure 29)

**Figure 29: Feature Construction menu**








Figure 30: After select the points in the second image, the measurement is complete

- 14) If you are finished with measurement, you can save the edits to the vector layer  
(Figuur 26)

### 2.3.3 Smart click measurement – Point measurement

- 1) Add a point vector data layer to the map where you want to add the measurement.
- 2) Open a image which the object is visible what should be measured.
- 3) Enable smart click measurement in the CycloMedia Options – Measurement menu.

(Figure 31)




Figure 31: Enable smart click measurement

- 4) Right click on the point vector layer and select: 'Edit Features -> Start Editing' (Figure 20)
- 5) Select the point layer in the Create Features form to start a point measurement. (Figure 21)
- 6) Select the point you want to measure in the image. (Figure 32)




Figure 32: Point measurement (smart click)

- 7) The selected measurement details form contains information about the measurement. (Figure 33)

**Selected Measurement Details**

Selected measurement details:

Number: 1

Position: 185085.84, 577035.69, 5.23

$\sigma(x,y,z)[m]$ : 0.11, 0.03, 0.06

Matches:


Reliability: ●

Observations:

ImageId	Image- $\sigma(x,y,z)[m]$	
5D1ZB56H	0,01 0,00 0,01	✖
5D1ZB59G	0,01 0,00 0,01	✖
5D1ZB56Q	0,01 0,00 0,01	✖

Figure 33: Selected Measurement Details form (Smart click)

- 8) You can check the other images which are found by smart click by clicking on the image and click on <Show>. (Figure 34)



**Figure 34: Check results found by smart click**


- 9) It is now possible to change correspondence points found by smart click.
- 10) It is also possible for add or remove observation points.
- 11) If you want to add more observation points, open a new image and select in that image the point you want to measure.
- 12) If you are finished, Click the <Close> button down the 'Selected Measurement Details' form. (Figure 34)
- 13) The measurement point is now added, if you want, you can now measure a second point at the same way.
- 14) If you are finished with measurement, you can save the edits to the vector layer. (Figure 26)

#### 2.3.4 Smart click measurement – Line / Surface measurement

- 1) Add a line or a polygon vector data layer to the map where you want to add the measurement.
- 2) Open a image which the object is visible what should be measured.
- 3) Enable smart click measurement in the CycloMedia Options – Measurement menu. (Figure 31)
- 4) Right click on the line or polygon vector layer and select: 'Edit Features -> Start Editing' (Figure 20)



- 5) Select the line or polygon layer in the Create Features form to start a line or a surface measurement. (Figure 21)
- 6) Select the first point in the image which you want to measure. (Figure 35)



**Figure 35: Line or polygon measurement after adding first point**

- 7) The selected measurement details form contains information about the measurement. (Figure 33)
- 8) If you want to edit or check some observation points, first click on the <Edit> button.
- 9) You can check the other images which are found by smart click by clicking on the image and click on <Show>. (Figure 34)
- 10) It is now possible to change correspondence points found by smart click.
- 11) It is also possible for add or remove observation points.
- 12) If you want to add more observation points, open a new image and select in that image the point you want to measure.
- 13) If you want to add more measurement points, first close the measurement point.
- 14) Then you select the second and the third point you want to measure, until you have done all the points you want to measure.
- 15) For each measurement point that you add, you must first check if it is good.
- 16) Click on the "finish sketch" button of the "Feature Construction" menu to close the measurement. (Figure 29)
- 17) If you are finished with measurement, you can save the edits to the vector layer (Figure 26)

### 2.3.5 Import a measurement back in a Cyclorama

You have to do these steps to import a measurement back in a Cyclorama:

- 1) Select the 'Edit tool' button in the editor menu and a measurement can now be selected for importing into a cyclorama. (Figure 36)




Figure 36: Editor menu

- 2) Select a feature and the Measurement is placed back in the cyclorama. (Figure 37)





Figure 37: Measurement in cyclorama

- 3) Click on the feature and on the right mouse button and select in the menu 'Edit Vertices' to edit the measurement in the cyclorama. (Figure 38)



**Figure 38: Select Edit Vertices**

- 4) It is now possible to edit the measurement in the cyclorama or in the map.
- 5) If you want to edit a measurement point in the cyclorama, select that point in the map.
- 6) Click in the 'Editor' menu on the 'Sketch Properties' button for view the values of the measurement points. (Figure 39)



**Figure 39: Editor menu - Sketch properties**

- 7) You can change the measurement values by selecting a point. The M value is the reference to the number of that point in the cyclorama . (Figure 40)

Edit Sketch Properties					
	#	X	Y	Z	M
<input type="checkbox"/>	0	185079,645	577029,552	4,879	1,000
<input type="checkbox"/>	1	185078,970	577029,825	4,891	2,000
<input checked="" type="checkbox"/>	2	185079,238	577030,676	3,925	3,000
<input type="checkbox"/>	3	185079,989	577030,412	3,936	4,000

**Figure 40: Edit Sketch properties**